

Can't get ssh and wu-ftp to work together

Source: <http://www.derkeiler.com/Newsgroups/comp.security.ssh/2003-10/0330.html>

From: Richard Brandt (richard1.brandt_at_attbi.com)

Date: 10/26/03

Date: Sun, 26 Oct 2003 18:42:45 GMT

I am trying to follow the example in the "SSH-The Secure Shell" book for tunneling the control channel thru ssh.

I setup the initial tunnel per the example

```
client% ssh -L2001:server:21 server
```

This works fine

```
client% ftp -vd localhost 2001
```

This also works fine (login has no problems)

but when I try to do any commands like "ls" it fails with

```
ftp:setsockopt (ignored ): permission denied
```

```
----> PASV
```

```
Entering passive mode(192,168,1,50,232,45)
```

```
ftp:connect: Connection refused
```

I see that the client does try to connect to the server at the right address and port but gets a RST

When I run netstat on the server it shows LISTENING with the local address 127.0.0.1:59437

So I'm guessing the connection is refused since the server is just listening on the loopback

But I don't know what else to change.

I have wu-ftp 2.6.1-18 on Linux

ftppass looks like this

```
class Test_guest_class guest *
limit Test_guest_class 2 Any /var/ftp/too-many.msg
# noretrieve /*
loginfails 2
private no
banner /var/ftp/banner.msg
hostname ftpserver
email root@localhost
message /welcome.msg LOGIN
message .message CWD=*
readme README* LOGIN
readme README* CWD=*
chmod no anonymous,guest
delete no anonymous,guest
```

comp.security.ssh: Can't get ssh and wu-ftp to work together

```
overwrite no anonymous,guest
rename no anonymous,guest
umask no guest
passwd-check rfc822 warn
log commands guest
log security guest
log transfers anonymous,guest,real inbound
log transfers anonymous,guest,real outbound
guestgroup rftpusers
limit-upload guest 10000
limit-download guest 1
file-limit in 1 Test_guest_class
file-limit out 0 Test_guest_class
pasv-allow guest *
port-allow all
passive address 192.168.1.50 0.0.0.0/0
```

Richard Brandt