

## Re: SFTP in batch mode

**Source:** <http://www.derkeiler.com/Newsgroups/comp.security.ssh/2002-10/2741.html>

---

**From:** zeb ([thierry.constant1@free.fr](mailto:thierry.constant1@free.fr))

**Date:** 10/26/02

From: "zeb" <[thierry.constant1@free.fr](mailto:thierry.constant1@free.fr)>

Date: Sat, 26 Oct 2002 10:11:28 +0200

OK. thank you very much ...

"Yang xiao" <[yang2002\\_99@yahoo.com](mailto:yang2002_99@yahoo.com)> a écrit dans le message de news:  
55c6e631.0210241044.2f545ff1@posting.google.com...

> "zeb" <[thierry.constant1@free.fr](mailto:thierry.constant1@free.fr)> wrote in message  
news:<3db5ab5e\$0\$232\$626a54ce@news.free.fr>...

> > Hi,

> >

> > I want to transfert , with SFTP or SCP ( SUN -> HP-UX) some files with  
a

> > script

> > every night.

> >

> > with nothing:

> > I am prompted for a password

> >

> > with key-gen, I generated a ~/.ssh/identity.pub , which I copy to the

> > remote host in ~/.ssh/authorized\_keys

> > I am prompted for the pass phrase

> >

> > what I have to do to have a real batch mode ??

> >

> > Thanks in advance

>

>

> 1. ssh-keygen a key without a pass phrase.

> or

> 2. use ssh-agent (man ssh-agent, ssh-add)

>

> basically, you need to generate a ssh-agent to hold the keys and pass  
> the environment variables to the batch jobs.

>

> \$ ssh-agent > ~/env-info #take a look in this file you

> will understand, and for c shells, etc. use ssh-agent -c

> \$ ssh-add BatchKey

>

> input key phrase. Now, in the batch script:

comp.security.ssh: Re: SFTP in batch mode

>  
> `#!/bin/ksh`  
> `source ~/env-info`  
> `scp ..`  
> `ssh ..`  
>  
> *Hope this helps.*  
>  
> *Yang*

---

- **Next message:** Macarie Neculai: "Re: I cannot connect to a host, but I can connect to other hosts"
- **Previous message:** :"SSH API for C"
- **In reply to:** Yang xiao: "Re: SFTP in batch mode"
- **Messages sorted by:** [ date ] [ thread ] [ subject ] [ author ] [ attachment ]